Museum Integration API / Interface

Raspberry Pi + IMX219 High-Speed Camera -> Polymerization Exhibit

Table of Contents

0) F	urpose & Scope	2
1) S	ystem Overview (Contract Boundaries)	2
2) Hardware Integration API		2
	2.1 Connectors & Pin Map	2
	2.2 Electrical Levels	2
	2.3 Raspberry Pi GPIO Contract	3
	2.4 Camera Mounting & Optics	3
3) T	iming API	3
	3.1 Event Sequence (Nominal)	3
	3.2 Capture Window Policies	3
4) Software/API Surface on Raspberry Pi		3
	4.1 Required Software	3
	4.2 Command-Line Capture API (contract)	3
	4.3 GPIO Trigger Daemon (service)	4
	4.4 Playback API	4
	4.5 Output Artifacts (contract)	4
5) A	rduino-Side Interface	4
	5.1 Firmware Behavior (integration contract)	4
	5.2 Serial Command Set (for ops & debug)	4
6) C	Configuration Profiles (Examples)	4
	6.1 High-FPS, Narrow View (default)	4
	6.2 Wider View, Mid-FPS	5
	6.3 Presentation-Optimized (trimmed)	5
7) Installation & Bring-Up (Step-by-Step)		5
8) V	alidation & Acceptance Tests	5
9) C	perations	5
10)	Appendix: Reference Snippets	6
	10.1 raspiraw example with timestamps	6
	10.2 Minimal GPIO wait (Python)	6
	10.3 Arduino trigger (concept)	6
11)	FAQ	6

0) Purpose & Scope

This document defines a repeatable integration interface ("API") so a museum technologist can connect a Raspberry Pi + IMX219 camera to the existing polymerization exhibit and get a reliable, high-fps capture -> slow-motion playback loop. It specifies hardware connectors, electrical levels, timing, software commands, configuration, expected I/O artifacts, and validation tests. It assumes an existing droplet/UV prototype with Arduino-based control.

It is an **integration contract** across electronics, GPIO, serial commands, and command-line tools.

1) System Overview (Contract Boundaries)

Actors

- **Exhibit Controller (Arduino Nano)**: runs droplet, sensor, UV logic; emits a *trigger pulse* when a droplet enters the filmed region.
- Capture Host (Raspberry Pi 3): runs modified raspiraw, listens for trigger on GPIO17, captures ~100 ms at ~950–1000 fps, saves raw frames + timestamps, then renders slow-motion.
- Camera (Sony IMX219): rotated 90° to align rolling shutter with vertical droplet path; uses small vertical ROI to hit ~1 kfps.

Key Interfaces

- **Electrical trigger**: Arduino A3 -> (voltage divider) -> Pi GPIO17 (rising edge).
- **Serial control** (optional, for debug/ops): Pi/Computer ↔ Arduino over USB CDC; simple text commands (e.g., go, stop).
- File outputs: frames & timestamps in RAM-disk (/dev/shm), then playback via OpenCV scripts.

2) Hardware Integration API

2.1 Connectors & Pin Map

- SENSE4 header on exhibit shield (chosen to avoid collisions with existing wiring):
 - o Pin 1: Vin (not used).
 - o **Pin 2: Arduino A3** (digital output *trigger*).
 - o **Pin 3: GND** (must tie Arduino and Pi grounds together).

2.2 Electrical Levels

- Arduino -> Pi trigger level shift: passive divider 5 V -> ~3.2 V.
 - o Example divider: 2 k Ω (top) to Arduino A3, 1 k Ω (bottom) to GND; midpoint to Pi GPIO17.
 - Result ≈ 5 V × (1 k Ω / (2 k Ω + 1 k Ω)) ≈ 3.3 V (safe for Pi input).

2.3 Raspberry Pi GPIO Contract

- Trigger input pin: GPIO17
- Edge: Rising edge starts capture.
- Pulse width requirement: ≥ 5 ms (debounced by firmware; longer is fine). If in doubt: 20–50 ms pulse width is robust.

2.4 Camera Mounting & Optics

- Sensor rotation: 90° so the vertical ROI tracks droplet fall.
- ROI height presets: 64 / 128 / 192 rows (trade coverage vs. fps). Default: 64 rows for ~950–1000 fps.
- Focus: set with a hanging droplet under exhibit lighting; confirm edges are crisp within ROI.

3) Timing API

3.1 Event Sequence (Nominal)

[Droplet detected] -> Arduino emits A3 HIGH -> Pi sees rising edge on GPIO17 -> raspiraw starts capture (target 100 ms @ ~1000 fps) -> frames buffered to RAM -> Pi writes timestamps.csv and RAW frames -> playback script builds slow-motion -> HDMI display.

3.2 Capture Window Policies

- Baseline: pre-armed, fixed 100 ms capture.
- Trimmed options (for faster turnaround):
 - P10/P90 policy: pre-delay ~28 ms, record ~60 ms (edge miss risk bounded by chosen percentiles).
 - Mild trim: pre-delay ~10 ms, record ~80 ms.
- Fallback: if no frames arrive within 250 ms after trigger, abort and log an error.

4) Software/API Surface on Raspberry Pi

4.1 Required Software

- Modified raspiraw (IMX219-only build with dynamic ROI & ring buffer).
- Python 3 + OpenCV + NumPy (playback & utilities).
- dcraw or equivalent for RAW→TIFF (where applicable).

4.2 Command-Line Capture API (contract)

```
CLI: raspiraw [options...]
```

Required options:

```
-md 7 -> IMX219 mode (compatible with small vertical ROI)
-t <ms> -> capture duration (e.g., 100)
-fps <fps> -> requested frame rate (e.g., 1000)
-h <rows> / -w <cols> -> ROI rows/cols (e.g., -h 64 -w 640)
-o /dev/shm/out.%06d.raw -> RAW frame pattern in RAM
```

```
    -ts /dev/shm/tstamps.csv -> timestamp log
    -g <gain> -> sensor analog gain (e.g., 1–8)
    -eus <μs> -> exposure in microseconds (e.g., 750)
    -regs "0171,01;0170,01" -> example register tweaks used in testing
```

Canonical example:

```
./raspiraw -md 7 -t 100 -ts /dev/shm/tstamps.csv -hd0 /dev/shm/hd0.32k \
-h 64 -w 640 --fps 1000 -sr 1 --regs "0171,01;0170,01" -g 1 -eus 750 \
-o /dev/shm/out.%06d.raw
```

4.3 GPIO Trigger Daemon (service)

- A small Python service arms capture and waits on GPIO17 rising edges.
- On trigger: spawn the raspiraw command with configured ROI/exposure, then enqueue post-processing.
- On completion: notify the **playback** process.

4.4 Playback API

- **Debug:** player_tiff_keyboard.py / player_tiff_keyboard_interp.py (interactive).
- **Exhibit mode:** player_pin.py (or a kiosk script) to autoplay most recent capture on HDMI.
- Interpolation factor (optional): ×4 for smoother slow-motion on public display.

4.5 Output Artifacts (contract)

- /dev/shm/tstamps.csv: frame index + µs timestamp per frame.
- /dev/shm/out.XXXXXX.raw: contiguous RAW frames.

5) Arduino-Side Interface

5.1 Firmware Behavior (integration contract)

- On droplet detect: assert A3 HIGH once for a single event; de-assert after UV completes.
- Avoid multiple pulses per droplet; minimum inter-event spacing: ≥ 1 s.

5.2 Serial Command Set (for ops & debug)

```
help # list commands
status # print key parameters
set drnum <N> # set number of drops in a run (if used)
set drprt <P> # set droplet period (ms) or profile param
go # start a programmatic run (will emit A3 when appropriate)
stop # stop run and de-energize actuators
```

6) Configuration Profiles (Examples)

6.1 High-FPS, Narrow View (default)

```
ROI: 64 rows, 640 cols
FPS: 1000
Exposure: 750 μs
```

Gain: 1-4 (tune to lighting)
Capture window: 100 ms

6.2 Wider View, Mid-FPS

ROI: 128 rows, 820 cols (example)

FPS: 500-660

Exposure: 900-1100 μs (ensure Frame_Length ≥ exposure+4)

Capture window: 120 ms

6.3 Presentation-Optimized (trimmed)

ROI: 64 rows FPS: 1000

Record length: 60-80 ms
Interpolation(optional): x2

7) Installation & Bring-Up (Step-by-Step)

- 1. Tie grounds at SENSE4 Pin 3.
- 2. Wire A3 -> divider -> **GPIO17**; verify ~3.2 V at Pi when A3 HIGH.
- 3. Mount & rotate IMX219 by 90°. Confirm lens focus & ROI coverage.
- 4. Boot Pi; install packages; deploy modified raspiraw and Python scripts.
- 5. Run test signal.py to confirm clean rising-edge detection on GPIO17.
- 6. Dry-run capture using edge_detect_signal.py (fake/forced trigger) to validate file outputs.
- 7. Perform a live droplet/UV run; confirm /dev/shm outputs and HDMI playback.

8) Validation & Acceptance Tests

Electrical - Divider output 3.0–3.3 V on A3 HIGH; <0.8 V on LOW. - Pulse width \ge 5 ms; no chatter.

Timing - Achieves \geq 900 fps at ROI=64 with \leq 2 dropped frames per 100 ms run. - Visible droplet dwell \approx 38–40 ms within the UV region.

Function - On trigger, capture starts within ≤ 10 ms. - Files appear in /dev/shm.

Stress - 30 back-to-back runs without crash; temperature within safe range; no fps drift.

9) Operations

- **Reset policy:** if capture fails (no frames), auto-retry once; then prompt for service.
- Log files: /var/log/exhibit-cam/*.log for trigger/capture/playback events.
- Safe shutdown: power UV off before any software restart.

10) Appendix: Reference Snippets

10.1 raspiraw example with timestamps

```
./raspiraw -md 7 -t 100 -ts /dev/shm/tstamps.csv -hd0 /dev/shm/hd0.32k \
  -h 64 -w 640 --fps 1000 -sr 1 --regs "0171,01;0170,01" -g 1 -eus 750 \
  -o /dev/shm/out.%06d.raw
10.2 Minimal GPIO wait (Python)
import RPi.GPIO as GPIO, subprocess, time
PIN=17
GPIO.setmode(GPIO.BCM); GPIO.setup(PIN, GPIO.IN, pull up down=GPIO.PUD DOWN)
while True:
    GPIO.wait_for_edge(PIN, GPIO.RISING)
    subprocess.run([
        "./raspiraw", "-md", "7", "-t", "100", "--fps", "1000",
        "-h", "64", "-w", "640", "-g", "1", "-eus", "750",
        "-ts", "/dev/shm/tstamps.csv", "-o", "/dev/shm/out.%06d.raw"
    1)
    subprocess.run(["python3","player pin.py"]) # or your renderer
10.3 Arduino trigger (concept)
const int TRIG=A3; void setup(){ pinMode(TRIG, OUTPUT); digitalWrite(TRIG, LOW);}
void loop(){
  if(/* droplet detected */){
    digitalWrite(TRIG, HIGH); // start capture
    // UV on ...
    delay(50);
    // UV off ...
    digitalWrite(TRIG, LOW); // done
}
```

11) FAQ

- Q: Can we move the trigger to a different Pi pin?
 A: Yes, but update the daemon/script and retain rising-edge semantics.
- Q: Can we widen the view for a bigger scene?
 A: Increase ROI rows (e.g., 128/192). Expect fps to drop roughly inversely with ROI height.
- Q: How do we make playback smoother?
 A: Use the interpolation player at ×4; it inserts in-between frames for display.

End of API